1.8.13
ARDUINO
Genuino
AN OPEN PROJECT WRITTEN, DEBUGGED,
AND SUPPORTED BY ARDUINO.CC AND
THE ARDUINO COMMUNITY WORLDWIDE
LEARN MORE ABOUT THE CONTRIBUTORS
OF ARDUINO.CC on arduino.cc/credits


Board: "Arduino Uno"
Port: "COM5 (Arduino Uno)"
Get Board Info
Programmer: "AVR ISP"
Burn Bootloader
Boards Manager...
Arduino Yún
Arduino Uno
Arduino Duemilanove or Diecimila
Arduino Nano

Board: "Arduino Uno"
Port: "COM5 (Arduino Uno)"
Get Board Info
Serial ports
COM5 (Arduino Uno)


Board Info
BN: Arduino Uno
VID: 2341
PID: 0043
SN: 7583435343035111C0E0
OK


Blink | Arduino 1.8.13
File Edit Sketch Tools Help
Blink
/*
Blink
Turns an LED on for one second, then off for one second, repeatedly.
Most Arduinos have an on-board LED you can control. On the UNO, MEGA and ZERO
it is attached to digital pin 13, on MKR1000 on pin 6. LED_BUILTIN is set to
the correct LED pin independent of which board is used.
If you want to know what pin the on-board LED is connected to on your Arduino
model, check the Technical Specs of your board at:
https://www.arduino.cc/en/Main/Products
modified 8 May 2014
by Scott Fitzgerald
modified 2 Sep 2016
by Arturo Guadalupi
modified 8 Sep 2016
by Colby Newman
This example code is in the public domain.
http://www.arduino.cc/en/Tutorial/Blink
*/
// the setup function runs once when you press reset or power the board
void setup() {
// initialize digital pin LED_BUILTIN as an output.
pinMode(LED_BUILTIN, OUTPUT);
Problem uploading to board. See http://www.arduino.cc/en/Guide/Troubleshooting#upload for suggestions.
Copy error messages
Problem uploading to board. See http://www.arduino.cc/en/Guide/Troubleshooting#upload for suggestions.
1
Arduino Uno on COM5